

## SNS COLLEGE OF TECHNOLOGY, COIMBATORE –35 (An Autonomous Institution) DEPARTMENT OF COMPUTER SCIENCE AND ENGINEERING



#### Non restoring Division Algorithm

Instead of the quotient digit set  $\{0, 1\}$ , the set  $\{-1, 1\}$  is used by the non-restoring division. The nonrestoring division algorithm is more complex as compared to the restoring division algorithm. But when we implement this algorithm in hardware, it has an advantage, i.e., it contains only one decision and addition/subtraction per quotient bit. After performing the subtraction operation, there will not be any restoring steps. Due to this, the numbers of operations basically cut down up to half. Because of the less operation, the execution of this algorithm will be fast. This algorithm basically performs simple operations such as addition, subtraction. In this method, we will use the sign bit of register A. 0 is the starting value/bit of register A.



Now we will learn steps of the non-restoring

division algorithm, which are described as follows:



# SNS COLLEGE OF TECHNOLOGY, COIMBATORE –35 (An Autonomous Institution)



### DEPARTMENT OF COMPUTER SCIENCE AND ENGINEERING

**Step 1:** In this step, the corresponding value will be initialized to the registers, i.e., register A will contain value 0, register M will contain Divisor, register Q will contain Dividend, and N is used to specify the number of bits in dividend.

**Step 2:** In this step, we will check the sign bit of A.

**Step 3:** If this bit of register A is 1, then shift the value of AQ through left, and perform A = A + M. If this bit is 0, then shift the value of AQ into left and perform A = A - M. That means in case of 0, the 2's complement of M is added into register A, and the result is stored into A.

Step 4: Now, we will check the sign bit of A again.

**Step 5:** If this bit of register A is 1, then Q[0] will become 0. If this bit is 0, then Q[0] will become 1. Here Q[0] indicates the least significant bit of Q.

Step 6: After that, the value of N will be decremented. Here N is used as a counter.

Step 7: If the value of N = 0, then we will go to the next step. Otherwise, we have to again go to step 2.

**Step 8:** We will perform A = A + M if the sign bit of register A is 1.

**Step 9:** This is the last step. In this step, register A contains the remainder, and register Q contains the quotient.

#### For example:

In this example, we will perform a Non-Restoring Division algorithm with the help of an Unsigned integer.

- 1. Dividend = 11
- 2. Divisor = 3
- 3. -M = 11101

### N M A Q Action

- 4 00011 00000 1011 Begin 00011 00001 011\_ Shift left AQ 00011 11110 011\_ A = A - M
- 3 00011 11110 0110 Q[0] = 0 00011 11100 110\_ Shift left AQ 00011 11111 110 A = A + M
- 2 00011 11111 1100 Q[0] = 0 00011 11111 100\_ Shift left AQ 00011 00010 100\_ A = A +M



## SNS COLLEGE OF TECHNOLOGY, COIMBATORE –35 (An Autonomous Institution)



DEPARTMENT OF COMPUTER SCIENCE AND ENGINEERING

- 1 00011 00010 1001 Q[0] = 1 00011 00101 001\_ Shift left AQ
- $00011\ 00010\ 001\_A = A M$
- 0 00011 00010 0011 Q[0] = 1

So, register A contains the remainder 2, and register Q contains the quotient 3.